

INSTRUCTIONS FOR OBTAINING YOUR IP ADDRESS- WINDOWS XP

Please follow the instructions below to obtain your IP address, if you have any questions please contact the NZ Relay helpdesk Helpdesk@NZRelay.co.nz


1. Select **Start** then **Run**



2. Type **cmd**



3. Type **ipconfig /all**



4. There may be a few IP addresses to choose from, please send us the IP address which is not in the following ranges:

- 10.0.0.0 – 10.255.255.255
- 172.16.0.0 – 172.31.255.255
- 192.168.0.0 – 192.168.255.255

If you are unsure please send us all your IP addresses and we will be able to identify the correct one.

```
Ethernet adapter Local Area Connection:
    Connection-specific DNS Suffix . : 
    Description . . . . . : Intel(R) PRO/100 UE Network Connecti
on
    Physical Address. . . . . : 00-0E-7B-D2-3C-1F
    Dhcp Enabled. . . . . : No
    IP Address. . . . . : 193.0.11.72
    Subnet Mask . . . . . : 255.255.255.0
    Default Gateway . . . . . : 193.0.11.254
    DNS Servers . . . . . : 193.0.11.57
                          193.0.11.58

Ethernet adapter Wireless Network Connection:
    Media State . . . . . : Media disconnected
    Description . . . . . : Intel(R) PRO/Wireless 2915ABG Networ
k Connection
    Physical Address. . . . . : 00-12-F0-F5-1F-4F

Ethernet adapter Wireless Network Connection 2:
    Media State . . . . . : Media disconnected
    Description . . . . . : Sierra Wireless AC595 1xEV-DO Networ
k Adapter
    Physical Address. . . . . : 00-A0-D5-FF-FF-85

PPP adapter - Telecom 3G:
    Connection-specific DNS Suffix . : 
    Description . . . . . : WAN (PPP/SLIP) Interface
    Physical Address. . . . . : 00-53-45-00-00-00
    Dhcp Enabled. . . . . : No
    IP Address. . . . . : 166.179.6.106
    Subnet Mask . . . . . : 255.255.255.255
    Default Gateway . . . . . : 166.179.6.106
    DNS Servers . . . . . : 202.27.158.40
                          202.27.156.72
    NetBIOS over Tcpip. . . . . : Disabled
```